

The logo for VG Instruments features the text "VG Instruments" in a bold, red, 3D-style font. The text is set against a background of a blue and purple gradient with a bright light source on the right, creating a lens flare effect. The letters have a slight shadow and a metallic sheen.

VG Instruments

VG Soul Tenor Saxophone

NI Kontakt Sound Library, WAV

- VG Soul Tenor Saxophone, NI KONTAKT Sound Library. Wav and .nki format.
- More than 170 unique samples
- WAV files can be used directly in your DAW, or any other sampler plugin for further editing
- Set up to work with breath controllers (TEControl), wind controllers (EWI, Aerophone) and MIDI keyboard controllers.
- Each note was individually sampled to achieve maximum realism
- Custom designed, unique GUI
- VG Soul Tenor Saxophone requires the full retail version of Kontakt 5.1 or later, Kontakt Player not supported
- Recorded sample quality: 24 bit / 48 kHz
- Reverb, delay, stereo control to fit the saxophone in every mix
- Best Balance of Natural Velocity Resolution and Data Size
- Library Size: 173 MB

Installation Notes

1. Uncompress VGSoulSaxophoneTenor_.zip using your favorite archiving utility.
2. Upload VG_Soul_Saxophone_Tenor_.nki instrument into Kontakt from VG_Soul_Saxophone_Tenor_ folder – drag and drop, or double-click from Kontakt browser. Activation is not necessary.



Choose a basic instrument: Sax 1, Sax 2,



Keyboard / Breath button changes performance modes:

Playing on keyboard instrument / Playing with breath or wind controller (TEControl, EWI, Aerophone)

If your MIDI keyboard doesn't have Mod wheel, click the "Mod Wheel" button to turn it off.



Set Control Change (CC) number in MIDI CC box in accordance to your breath or wind controller (EWI, TEControl) settings. Normally breath controllers are set to send MIDI CC2, CC11 or CC7 messages types.



Reverb ON/OFF, Delay ON/OFF and Stereo ON/OFF switch on/off corresponding effects.

Regulators change the level of corresponding effects.

