

The logo for VG Instruments features the text "VG Instruments" in a bold, red, 3D-style font. The text is set against a dark blue background with a bright, glowing light source on the right, creating a lens flare effect that illuminates the scene from behind. The overall aesthetic is sleek and modern.

VG Instruments

VG Jazz Baritone Saxophone

NI Kontakt Sound Library, WAV

- VG Jazz Baritone Saxophone NI KONTAKT Sound Library. Wav and .nki format.
- More than 280 unique samples
- WAV files can be used directly in your DAW, or any other sampler plugin for further editing
- Set up to work with breath controllers (TEControl), wind controllers (AKAI EWI, Roland Aerophone AE-10, Pro AE-30, Yamaha WX, etc.) and MIDI keyboard controllers.
- Up to 4 velocity layers per key
- Each note was individually sampled to achieve maximum realism
- Custom designed, unique GUI
- VG Jazz Baritone Saxophone requires the full retail version of Kontakt 5.6.8 or later. Kontakt Player is not supported
- Recorded sample quality: 24 bit / 44.1 kHz
- Effects: Vibrato, Growl, Subtone
- Reverb, delay, stereo control to fit the saxophone in every mix
- Best Balance of Natural Velocity Resolution and Data Size
- Library Size: 312 MB

Installation Notes

1. Uncompress VGJazzBaritoneSaxophone_.zip using your favorite archiving utility.
2. Upload VG_JazzBaritoneSaxophone_.nki instrument into Kontakt from VGJazzBaritoneSaxophone_ folder – drag and drop, or double-click from Kontakt browser. Activation is not necessary.



Keyboard / Breath button changes performance modes:
 Playing on keyboard instrument / Playing with breath or wind controller
 (TEControl, EWI, Aerophone, Yamaha WX, etc.)

If your MIDI keyboard doesn't have Mod wheel,
 click the **"Mod Wheel" button** to turn it off.

Set Control Change (CC) number in **CC# box** in accordance
 to your breath or wind controller (EWI, TEControl) settings.
 Normally breath controllers are set to send MIDI CC2, CC11
 or CC7 messages types.



EFFECTS
Reverb ON/OFF, Delay ON/OFF and Stereo ON/OFF
 switch on/off corresponding effects.

Regulators change the level of corresponding effects.



Sax 1 ON/OFF, Sax 2 ON/OFF buttons


Choose a basic instrument: Sax1, Sax2.



TIMBRE

Dark, Normal, Bright

Make the tone darker or brighter using these buttons.




GROWL

This panel allows to add the Growl effect to your sustain samples via a fader or mod wheel.



VIBRATO

This panel allows to add the Vibrato effect to your sustain samples via a fader or mod wheel.



SUBTONE ON/OFF button

switch on/off the Subtone effect..

