

The logo for VG Instruments features the text "VG Instruments" in a bold, red, 3D-style font. The text is set against a dark blue background with a bright, glowing light source on the right side, creating a lens flare effect that illuminates the scene from behind the text.

# VG Instruments

## VG Jazz Bass Clarinet

NI Kontakt Sound Library, WAV

- VG Jazz Bass Clarinet NI KONTAKT Sound Library, wav and nki format.
- More than 250 unique samples
- WAV files can be used directly in your DAW, or any other sampler plugin for further editing
- Set up to work with breath controllers (TEControl), wind controllers (AKAI EWI, Roland Aerophone AE-10, Pro AE-30, Yamaha WX, etc.) and MIDI keyboard controllers.
- Up to 3 velocity layers per key
- Each note was individually sampled to achieve maximum realism
- Custom designed, unique GUI
- VG Jazz Bass Clarinet requires the full retail version of Kontakt 5.6.8 or later. Kontakt Player is not supported
- Recorded sample quality: 24 bit / 48 kHz
- Effects: Vibrato, Growl, Subtone
- Reverb, delay, stereo control to fit the clarinet in every mix
- Best Balance of Natural Velocity Resolution and Data Size
- Library Size: 143 MB

### Installation Notes

1. Uncompress VGJazzBassClarinet\_.zip using your favorite archiving utility.
2. Upload VG\_JazzBassClarinet\_.nki instrument into Kontakt from VGJazzBassClarinet\_ folder – drag and drop, or double-click from Kontakt browser.

Activation is not necessary.



**Keyb / Brth button** changes performance modes:  
 Playing on keyboard instrument / Playing with breath or wind controller  
 (TEControl, EWI, Aerophone, Yamaha WX, etc.)

If your MIDI keyboard doesn't have Mod wheel,  
 click the **"ModW"** button to turn it off.

Set Control Change (CC) number in **CC# box** in accordance  
 to your breath or wind controller (EWI, TEControl) settings.  
 Normally breath controllers are set to send MIDI CC2, CC11  
 or CC7 messages types.



**EFFECTS**  
**Reverb ON/OFF, Delay ON/OFF and Stereo ON/OFF**  
 switch on/off corresponding effects.


Regulators change the level of corresponding effects.



**Clr 1 ON/OFF, Clr 2 ON/OFF buttons**  
 Choose a basic instrument: Clarinet 1, Clarinet 2.



**TIMBRE**  
**Dark, Normal, Bright**  
 Make the tone darker or brighter using these buttons.




## GROWL

This panel allows to add the Growl effect to your sustain samples via a fader or mod wheel.



## VIBRATO

This panel allows to add the Vibrato effect to your sustain samples via a fader or mod wheel.



## SUBTONE ON/OFF button

switch on/off the Subtone effect..

